

Guide Navigation

1. Supported Features for SwitchBot device.
2. How to link Linxura with SwitchBot.
3. How to use Linxura to control SwitchBot device.

SwitchBot Setup Guide Video Link:

1. Supported Features for the SwitchBot

SwitchBot Tilt Supported Actions

Actions	Supported Mode	Description
Click/Double Click	Tilt Fully Open	Fully opens.
	Tilt Close Down	Fully closes downwards.
	Tilt Close Up	Fully closes upwards.
	Set Tilt Up Position	Allows setting a specific tilt position between fully open and fully closed up.
	Set Tilt Down Position	Allows setting a specific tilt position between fully open and fully closed down.
Rotate Clockwise/Rotate Counterclockwise	Tilt Up Open	Tilts up between fully open and the closed-up position.
	Tilt Up Close	Tilts down between fully open and the closed-up position.
	Tilt Down Open	Tilts up between fully open and the closed-down position.
	Tilt Down Close	Tilts down between fully open and the closed-down position.

SwitchBot Curtain Supported Actions

Actions	Supported Mode	Description
Click/Double Click	Curtain Open	opens fully.
	Curtain Close	Closes fully.
	Set Curtain Position	Allows setting a specific curtain position.
Rotate	Curtain Open	Rotate to open the Curtain.

Clockwise/Rotate Counterclockwise	Curtain Close	Rotate to close the Curtain.
--	---------------	------------------------------

SwitchBot Bot Supported Actions


Actions	Supported Mode	Description
Click/Double Click	On	Turn on.
	Off	Turn off.
	Toggle On/Off	Toggles between on and off states.
	Press	Triggers a press action.

2. How to link Linxura with SwitchBot device.

Make sure your SwitchBot device is set up in the SwitchBot app and functioning properly.


Step 1:

Open your SwitchBot app and click 'Profile' in the bottom-right corner.



Step 2:

Click 'Preferences'.





Step 3:


For Android users, click on 'App Version' 11 times in a row until 'Developer Options' appears. For iOS users, click 'About' option and then click on 'App Version' 11 times in a row until 'Developer Options' appears.

Step 4:


Click 'Developer Options'.




Step 5:
Copy Token and Secret key.




Step 6:
Open your Linxura app and then select the Linxura you want to bind with SwitchBot.




Step 7:
Choose a button.




Step 8:
Click 'Select platform'.




Step 9:
Select 'SwitchBot' option.




Step 10:
Click 'Confirm'.




Step 11:
Paste the Token and Secret key obtained from
the SwitchBot app.



Step 12:
Click 'Confirm'.




Step 13:
Select the SwitchBot device and click 'Save'.




3. How to use Linxura to control SwitchBot device.


Step 1:
Click the '+' icon to add a Click Action.




Step 2:
Click 'Mode' and select one of the options.



Step 3:
Select one of the 'Mode' options.



Step 4:
Click 'Save' to save the Click Action settings.



Step 5:
You can follow the same steps to configure Double Click, Rotate Clockwise, and Rotate Counterclockwise.

You can now use Linxura to control your SwitchBot device!

